

NAME

fmtutil – manage TeX formats and Metafont bases, per-user
 fmtutil-sys – manage TeX formats and Metafont bases, system-wide
 mktexfmt – create a TeX format or Metafont base

SYNOPSIS

```
fmtutil [-user|-sys] [OPTION] ... [COMMAND]  

fmtutil-sys [OPTION] ... [COMMAND]  

fmtutil-user [OPTION] ... [COMMAND]  

mktexfmt FORMAT.fmt [BASE.base] FMTNAME.EXT
```

DESCRIPTION

fmtutil version r53340 (2020-01-07 00:55:32 +0100)

Rebuild and manage TeX fmts and Metafont bases, collectively called "formats" here. (MetaPost no longer uses the past-equivalent "mems".)

If the command name ends in mktexfmt, only one format can be created. The only options supported are **--help** and **--version**, and the command line must be either a format name, with extension, or a plain name that is passed as the argument to **--byfmt** (see below). The full name of the generated file (if any) is written to stdout, and nothing else.

If not operating in mktexfmt mode, exactly one command must be given, extensions should generally not be specified, no non-option arguments are allowed, and multiple formats can be generated, as follows.

By default, the return status is zero if all formats requested are successfully built, else nonzero.

OPTIONS

```
--sys use TEXMFSYS{VAR,CONFIG}  

--user use TEXMF{VAR,CONFIG}  

--cnffile FILE  

  read FILE instead of fmtutil.cnf (can be given multiple times, in which case all the files  

  are used)  

--fmdir DIR  

  write formats under DIR instead of TEXMF[SYS]VAR  

--no-engine-subdir  

  don't use engine-specific subdir of the fmdir  

--no-error-if-no-format exit successfully if no format is selected  

--no-error-if-no-engine=ENGINE1,ENGINE2,...  

  exit successfully even if a required engine  

  is missing, if it is included in the list.  

--no-strict  

  exit successfully even if a format fails to build  

--nohash  

  don't update ls-R files
```

- recorder**
pass the **--recorder** option and save .fls files
- quiet**
be silent
- catcfg**
(does nothing, exists for compatibility)
- dolinks**
(does nothing, exists for compatibility)
- force**
(does nothing, exists for compatibility)
- test** (does nothing, exists for compatibility)

Commands:

- all** recreate all format files
- missing**
create all missing format files
- refresh**
recreate only existing format files
- byengine ENGINE**
(re)create formats built with ENGINE
- byfmt FORMAT**
(re)create format FORMAT
- byhyphen HYPHENFILE**
(re)create formats that depend on HYPHENFILE
- enablefmt**
FORMAT[/ENGINE] enable FORMAT, as built with ENGINE
- disablefmt** FORMAT[/ENGINE] disable FORMAT, as built with ENGINE
If multiple formats have the same name and
different engines, /ENGINE specifier is required.
- listcfg**
list (enabled and disabled) configurations, filtered to available formats
- showhyphen** FORMAT
print name of hyphen file for FORMAT
- version**
show version information and exit
- help** show this message and exit

ENVIRONMENT

Explanation of trees and files normally used:

If **--cnffile** is specified on the command line (possibly multiple times), its value(s) are used. Otherwise, `fmtutil` reads all the `fmtutil.cnf` files found by running `'kpsewhich --all fmtutil.cnf'`, in the order returned by `kpsewhich`. Files passed in via **--cnffile** are first

tried to be loaded directly, and if not found and the file names don't contain directory parts, are searched via `kpsewhich`.

In any case, if multiple `fmtutil.cnf` files are found, all the format definitions found in all the `fmtutil.cnf` files are merged.

Thus, if `fmtutil.cnf` files are present in all trees, and the default layout is used as shipped with TeX Live, the following files are read, in the given order.

For `fmtutil-sys`:

```

TEXMFCONFIG $TEXLIVE/YYYY/texmf-config/web2c/fmtutil.cnf
TEXMFSYSVAR $TEXLIVE/YYYY/texmf-var/web2c/fmtutil.cnf
TEXMFLOCAL $TEXLIVE/texmf-local/web2c/fmtutil.cnf
TEXMFDIST $TEXLIVE/YYYY/texmf-dist/web2c/fmtutil.cnf

```

For `fmtutil-user`:

```

TEXMFCONFIG $HOME/.texliveYYYY/texmf-config/web2c/fmtutil.cnf
TEXMFVAR $HOME/.texliveYYYY/texmf-var/web2c/fmtutil.cnf
TEXMFHOME $HOME/texmf/web2c/fmtutil.cnf
TEXMFSYSCONFIG $TEXLIVE/YYYY/texmf-config/web2c/fmtutil.cnf
TEXMFSYSVAR $TEXLIVE/YYYY/texmf-var/web2c/fmtutil.cnf
TEXMFLOCAL $TEXLIVE/texmf-local/web2c/fmtutil.cnf
TEXMFDIST $TEXLIVE/YYYY/texmf-dist/web2c/fmtutil.cnf

```

(where `YYYY` is the TeX Live release version).

According to the actions, `fmtutil` might write to one of the given files or create a new `fmtutil.cnf`, described further below.

Where formats are written:

By default, format files are (re)written in `TEXMFSYSVAR/ENGINE` by `fmtutil-sys`, and `TEXMFVAR/ENGINE` by `fmtutil`, where `/ENGINE` is a subdirectory named for the engine used, such as "pdftex".

If the `--fmtdir=DIR` option is specified, `DIR` is used instead of `TEXMF[SYS]VAR`, but the `/ENGINE` subdir is still used by default.

In any case, if the `--no-engine-subdir` option is specified, the `/ENGINE` subdir is omitted.

Where configuration changes are saved:

If config files are given on the command line, then the first one given will be used to save any changes from `--enable` or `--disable`. If the config files are taken from `kpsewhich` output, then the algorithm is more complex:

- 1) If `$TEXMFCONFIG/web2c/fmtutil.cnf` or `$TEXMFHOME/web2c/fmtutil.cnf` appears in the list of used files, then the one listed first by `kpsewhich --all` (equivalently, the one returned by `kpsewhich fmtutil.cnf`), is used.
- 2) If neither of the above two are present and changes are made, a new config file is created in `$TEXMFCONFIG/web2c/fmtutil.cnf`.

In general, the idea is that if a given config file is not writable, a higher-level one can be used. That way, the distribution's settings can be overridden system-wide using `TEXMFLOCAL`, and system settings can be overridden again in a particular user's

TEXMFHOME.

Resolving multiple definitions of a format:

If a format is defined in more than one config file, then the definition coming from the first-listed `fmtutil.cnf` is used.

Disabling formats:

`fmtutil.cnf` files with higher priority (listed earlier) can disable formats in lower priority (listed later) `fmtutil.cnf` files by writing a line like

```
#! <fmtname> <enginename> <hyphen> <args>
```

in the higher-priority `fmtutil.cnf` file.

The `#!` must be at the

beginning of the line, with at least one space or tab afterward, and there must be whitespace between each word on the list.

For example, you can disable the `luajitlatex` format by creating the file `$TEXMFCONFIG/web2c/fmtutil.cnf` with the line

```
#! luajitlatex luajittex language.dat,language.dat.lua lualatex.ini
```

(As it happens, the `luajittex`-related formats are precisely why the **--no-error-if-no-engine** option exists, since `luajittex` cannot be compiled on all platforms.)

`fmtutil-user` (`fmtutil -user`) vs. `fmtutil-sys` (`fmtutil -sys`):

When `fmtutil-sys` is run or the command line option `-sys` is used, `TEXMFSYSCONFIG` and `TEXMFSYSVAR` are used instead of `TEXMFCONFIG` and `TEXMFVAR`, respectively. This is the primary difference between `fmtutil-sys` and `fmtutil-user`.

See <http://tug.org/texlive/scripts-sys-user.html> for details.

Other locations may be used if you give them on the command line, or these trees don't exist, or you are not using the original TeX Live.

Supporting development binaries

If an engine name ends with `"-dev"`, formats are created in the respective directory with the `-dev` stripped. This allows for easily running development binaries in parallel with the released binaries.

REPORTING BUGS

Report bugs to: tex-live@tug.org

TeX Live home page: <http://tug.org/texlive/>